

# Reciprocal Lattice

Basics

## Geometric Definition

- ▶ The reciprocal lattice is fundamental for all diffraction effects and other processes in a crystal lattice where momentum is transferred.
- ▶ The *reciprocal lattice* of any *geometrical point lattice* has a simple geometric definition:
  - It can be constructed by drawing the direct lattice, picking three sets of lattice planes ( $h^i, k^i, l^i$ ) ( $i=1,2,3$ ) that are not coplanar, and by constructing three vectors  $g_{h,k,l}$  which are perpendicular to the respective lattice planes and with a length (measured in  $\text{cm}^{-1}$ ) that is given by  $|g|=2\pi/d_{h,k,l}$ , with  $d_{h,k,l}$ =distance between the lattice planes ( $h,k,l$ ).
  - The three vectors thus obtained, if reduced to the three shortest ones possible (take three lattice planes with largest distance, i.e. lowest values of  $(h,k,l)$ ) define the reciprocal lattice.
- ▶ This is, of course, just a complicated way of saying:
  - Take the **(100)**, **(010)**, and the **(001)** planes, and use the vectors perpendicular to those planes with a length given by  $2\pi/d$  for these **{100}** type planes as the base vectors of the reciprocal lattice.

## The Reciprocal Lattice as Fourier Transform of the Regular Lattice

- ▶ The reciprocal lattice, however, is best looked at as the **Fourier transform** of the regular lattice. We are showing this by constructing the Fourier transform of a real *crystal*.
  - It is easier to look at a real crystal (not just a lattice) because otherwise you have to work with  $\delta$ -functions.
  - A real crystal has atoms. And atoms contain charge densities  $\rho(r)$ , or, if we start simple and one-dimensional,  $\rho(x)$ .
  - Now,  $\rho(x)$  must be periodic in  $x$ -direction with the lattice constant  $a$ :

$$\rho(x + na) = \rho(x), \quad n=0 \pm 1, \pm 2, \dots$$

- We thus can expand  $\rho(x)$  into a **Fourier series**, i.e.

$$\rho(x) = \sum_n \rho_n \cdot \exp \frac{i \cdot x \cdot n \cdot 2\pi}{a}$$

- The three-dimensional case, in analogy, can be written as

$$\rho(r) = \sum_G \rho_G \cdot \exp (i \cdot G \cdot r)$$

- The vector  $G$  so far is just a mathematical construct defining the "inverse" space needed for the Fourier transform.
- However, since we can always substitute for any  $r$  a vector  $r + T$  ( $T$ = translation vector of the lattice), or written out,  $r + n_1 a_1 + n_2 a_2 + n_3 a_3$  with  $n_i$ = integers and  $a_i$ = base vectors of the lattice defining the crystal, the product  $r \cdot G$  must not change its value if we substitute  $r$  with  $r + n_1 a_1 + n_2 a_2 + n_3 a_3$ .
- This requires that  $G \cdot T = 2\pi \cdot m$  with  $m$ = integer.
- ▶ This is essentially a definition of the vectors  $G$  that serve as the Fourier transforms of the vector  $T$ , i.e. the lattice in space. These *reciprocal lattice vectors*, as they are called, can be obtained from the base vectors defining the regular lattice in the following way:

- If we write  $G$  in components we obtain

$$G = h \cdot g_1 + k \cdot g_2 + l \cdot g_3$$

- With  $h, k, l$  integers.

- The vectors  $\underline{g}_1$ ,  $\underline{g}_2$ , and  $\underline{g}_3$  are then the *unit vectors* of the **reciprocal lattice**. (yes – they are underlined, you just don't see it with some fonts!)

If we now form the inner product of  $\underline{G} \cdot \underline{T}$ , e.g., for simplicity, with  $\underline{T} = n_1 \cdot \underline{a}_1$ , we obtain

$$(h \cdot \underline{g}_1 + k \cdot \underline{g}_2 + l \cdot \underline{g}_3) \cdot (n_1 \cdot \underline{a}_1) = 2\pi \cdot m$$

- For an arbitrary  $n_1$  this only holds if

$$\begin{aligned} \underline{g}_1 \cdot \underline{a}_1 &= 2\pi \\ \underline{g}_2 \cdot \underline{a}_1 &= \underline{g}_3 \cdot \underline{a}_1 = 0 \end{aligned}$$

In general terms, we have

$$\underline{g}_i \cdot \underline{a}_j = 2\pi \cdot \delta_{ij}$$

- With  $\delta_{ij}$ =**Kronecker** symbol, defined by:  $\delta_{ij}=0$  for  $i \neq j$  and  $\delta_{ij}=1$  for  $i=j$ .

The above equation is satisfied with the following definitions for the unit vectors of the reciprocal lattice:

$$\begin{aligned} \underline{g}_1 &= 2\pi \cdot \frac{\underline{a}_2 \times \underline{a}_3}{\underline{a}_1 \cdot \underline{a}_2 \cdot \underline{a}_3} \\ \underline{g}_2 &= 2\pi \cdot \frac{\underline{a}_3 \times \underline{a}_1}{\underline{a}_1 \cdot \underline{a}_2 \cdot \underline{a}_3} \\ \underline{g}_3 &= 2\pi \cdot \frac{\underline{a}_1 \times \underline{a}_2}{\underline{a}_1 \cdot \underline{a}_2 \cdot \underline{a}_3} \end{aligned}$$